


Access from Gmail on Android


The following instructions were verified against Android 6.0.1 and newer. Please remember to utilize username@dreamscape.com or mail.dreamscape.com where appropriate.

To set up Gmail on Android automatically:


1. Open Gmail.
2. In the top right corner, tap your profile picture and tap **Add another account**.
3. Choose "Other".



4. Enter your email address and tap **Next**.




5. Choose the account type and tap **Next**. To keep the copies of email messages on the server, select the **IMAP** option. If you do not want to keep them on the server, select **POP3**.




What type of account is this?

- Personal (POP3)
- Personal (IMAP)

- Specify your email account password and tap **Next**.
- The application will automatically fetch the incoming server settings. Select whether deleting emails from Inbox will also delete them from your Plesk server or not and tap **Next**.




Username
john_doe@example.com

Password
..... 

Server
example.com

Delete email from server


When I delete from Inbox 

Note: You may see the “Certificate not valid” warning if the mail server or domain is not secured with a valid SSL/TLS certificate. To proceed via HTTP, tap **Advanced** and then tap **PROCEED ANYWAY**.

- The application will automatically fetch the outgoing server settings. Tap **Next**.

Note: Here you may see the “Certificate not valid” warning again. To proceed via HTTP, tap **Advanced** and then tap **PROCEED ANYWAY**.

- Keep the default Gmail sync settings or change them and tap **Next**.



Sync frequency:

Every 15 minutes ▼

Notify me when email arrives

Sync email for this account

10. (Optional) Change the account name and/or specify the name that will be displayed on sent messages.

11. Tap **Next** to exit the setup.

The setup is done. You can see the new account in the list of accounts in Gmail.

To set up a Gmail on Android manually:

1. Open Gmail.
2. In the top right corner, tap your profile picture and tap **Add another account**.
3. Choose "Other".
4. Enter your email address and tap **Manual Setup**.



Add your email address

admin@example.com


Manual setup




NEXT >



5. Choose the account type and tap **Next**. To keep the copies of email messages on the server, select the **IMAP** option. If you do not want to keep them on the server, select **POP3**.



6. Specify your email account password and tap **Next**.




7. The next screen displays the incoming server settings. Specify the port number 110 for POP3 or 143 for IMAP and tap **Next**.

The screenshot shows an Android mobile application interface for configuring incoming server settings. At the top, there is a blue header with the text "Incoming server settings". Below the header, the settings are organized into several sections:

- USERNAME:** A text input field containing "admin@example.com".
- PASSWORD:** A text input field containing seven dots, indicating a masked password. Below it is a checkbox labeled "Show password" which is currently unchecked.
- SERVER:** A text input field containing "example.com".
- PORT:** A text input field containing "110".
- SECURITY TYPE:** A dropdown menu currently set to "STARTTLS".
- Delete email from server:** A section with a partially visible dropdown menu.

At the bottom of the screen, there is a navigation bar with a back arrow on the left and a "NEXT >" button on the right.

8. The next screen displays the outgoing server settings. Specify the port number 25 and tap **Next**.



9. When all the data is specified, your Android device will check the connection to the server and create your mail account. The new account will be displayed in the list of accounts in the Gmail application.